



Service Logic Editor Manual

SRE 3.3

Table of Contents

1	What's new / changed in SRE 3.3	1
1.1	New / changed in this <i>Service Logic Editor</i> Guide	2
2	Service Logic Editor	2
2.1	Introduction	2
2.2	Service Logic List	3
2.2.1	Development vs Releases	3
2.2.2	Opening and editing an existing Service Logic	4
2.2.3	Creating a new Service Logic	6
2.2.4	New in Rel 3.3: Importing a Service Logic	6
2.3	Using the Service Logic Editor	7
2.3.1	Service Logic Nodes Description	7
2.3.2	Changed in Rel 3.3: Mouse operations in the Build and Simulate Call tabs	12
2.3.3	Build tab	13
2.3.4	Simulate call tab	15
2.3.5	Simulate SIP tab	25
2.3.6	Simulate ENUM tab	27
2.3.7	Simulate HTTP tab	28
2.3.8	Simulate CDR tab	28
2.3.9	Validate tab	30
2.3.10	Traces tab	37
2.3.11	Release tab	37
2.3.12	Export tab	38
2.3.13	Properties tab	38
2.4	Selecting service logics for operations	38
2.4.1	Changed in Rel 3.3: Service Selection	38
2.4.2	Service Logic Node Override	40
2.4.3	Changed in Rel 3.3: Custom Endpoints for SIP and HTTP	40

All inquiries related to the features described in this document can be emailed to **support@netaxis.be**.

1 What's new / changed in SRE 3.3

This section presents the list of locations that have been added or modified concerning new/changed features in SRE 3.3 Release.

It allows users familiar with earlier releases to jump directly to these locations.

Warning

The section below provides working links to new/changed sections or locations **in this Service Logic Guide** document.

A similar section can be found in *SRE Admin Guide* and *Nodes Description* documents, with working links to the targeted sections/locations. You will need to open these other documents and look for their own *What's new in 3.3* section.

1.1 New / changed in this Service Logic Editor Guide

1. Expanding SLE background grid See [Changed in Rel 3.3: Mouse operations in the Build and Simulate Call tabs](#)
2. Mouse over a step number in the SL viewport slides the timeline table to show the corresponding step See [New in Rel 3.3: Focus on a step in the Timeline](#)
3. Simulation shows the sip manipulations (Call Descriptions with added log) See [New in Rel 3.3: SIP manipulations are logged in Call Descriptors of SIP nodes](#)
4. Improve logging for external queries See [New in Rel 3.3: Queries are logged in Call Descriptors of External Query nodes](#)
5. Custom endpoints for SIP (in *Service Logic / Service Selection*) See [Changed in Rel 3.3: Service Selection](#) and [Changed in Rel 3.3: Custom Endpoints for SIP and HTTP](#).
6. Simulation Timeline: table top 3 lines *Step - Service Logic - Node* frozen on the vertical scroll See [New in Rel 3.3 - Frozen headers in Timeline table](#)
7. Simulation Timeline: fix the tooltip window when clicking on it See [The Simulation Timeline](#)
8. Setting a user-defined suffix on the Service Logic import See [New in Rel 3.3: Importing a Service Logic](#)
9. Export / Import simulations See [New in Rel 3.3 — Exporting/importing simulations](#)

2 Service Logic Editor

2.1 Introduction

The Session Routing Engine (SRE) is a platform mainly based on SIP, built upon a Kamailio SIP Proxy server pluggable interface. It receives hundreds of call requests per second and provides routing responses.

When the SRE receives a call request, it applies a programmable service logic to route the call to the target destination or to reply to the originating equipment with redirect or rejection information. Once it has been translated, a response is sent to the requester containing the required information.


Note

Selecting the service logic(s) that the SRE will use in production is explained in the last section of this document : [Selecting service logics for operations](#). Defining proper setup by assigning the appropriate service logic to each interface communicating with the SRE is mandatory for efficient operations.

This document describes the Service Logic Editor, which allows creating and selecting service logics for the SRE to operate.

2.2 Service Logic List

From the main menu bar, select **Service Logic** to open the menu, then **Service Logic Editor** to open the **Service Logic List** page.



2.2.1 Development vs Releases

This page displays all the service logics present in the system. They are categorized along two modalities:

- The *Development* tab displays the service logics that are being developed, i.e. which remain editable.
- The *Releases* tab displays the service logics that have been released. They are frozen in new, non-editable, releases suitable for deployment.

Service Logic

LIST

Development Releases

Show 10 entries

Search: rben doc

Name	Description	Edit	Open	Clone	Delete
RBEN doc 1	[empty]	Edit	Open	Clone	Delete
rben doc 2	[empty]	Edit	Open	Clone	Delete
rben doc 3	[empty]	Edit	Open	Clone	Delete
rben doc 4	[empty]	Edit	Open	Clone	Delete
rben doc datetime	[empty]	Edit	Open	Clone	Delete
rben doc extraction	[empty]	Edit	Open	Clone	Delete
rben doc manipulation	[empty]	Edit	Open	Clone	Delete
rben doc records list	[empty]	Edit	Open	Clone	Delete
rben doc scratchpad	[empty]	Edit	Open	Clone	Delete

Showing 1 to 9 of 9 entries (filtered from 34 total entries)

Previous 1 Next

New Service Logic Import

The list can be filtered using the *Search* field (top right) ; it can be limited to a set number of items (*Show nn entries* on top left). *Previous / Next* buttons at the bottom right allow navigating through the pages.

The *New Service Logic* button (bottom left) allows the creation of a service logic from scratch (see below).

The *Import* button (bottom right) allows importing a service logic file (.slid) exported from another SRE system.

For each listed service logic, the following actions are available:

- **Edit** button: opens the service logic for editing
- **Open** button: opens the service logic only for simulation (no edition possible)
- **Clone** button: duplicates the service logic by creating a copy with a new name and description.
- **Delete** button: deletes the service logic (with Y/N confirmation).

2.2.2 Opening and editing an existing Service Logic


To open **and edit** an existing service logic, click the **Edit** button on the corresponding line.

This opens the Service Logic Editor page in *Edit* mode, showing the full set of function tabs:


- Build
- Simulate call
- Simulate SIP

- Simulate ENUM
- Simulate HTTP
- Simulate CDR
- Validate
- Release
- Traces
- Export
- Properties.

The selected service logic can be fully edited and managed (see [Using the Service Logic Editor](#) below).




Opening a SL in a development state that is, for whatever reason, also the active SL will show a warning:



To open an existing service logic **without editing features**, click the **Open** button on the corresponding line.


This opens the Service Logic Editor page in Run-only mode, showing only the Simulate tabs and Validate and Traces tabs. The selected service logic cannot be edited: only simulations will be able to run (see description of [Simulate call tab](#) and other Simulate tabs below).



2.2.3 Creating a new Service Logic

To create a new service logic, click the **New Service Logic** button (bottom left in *List* page).

This opens the **New Record** page, where you provide the Name and Description of the new service logic.



Click the **Save** button: this opens the Service Logic Editor page in Editor mode (showing the 7 tabs) to start designing the new service logic.

2.2.4 New in Rel 3.3: Importing a Service Logic

The **Import** button in the *List* page (see above) allows importing a service previously exported from a different SRE system.

A modal window Import opens where you can select the exported service logic file (.slid) stored on your system.

Import service logic

✕

File

Choisir un fichier
serviceLo..._suffix.slid

Select a previously exported service logic file.

Name for testI_created_my_own_suffix

testI_created_my_own_suffix

Suffix

_imported_2023-07-06 10:49:55

Can be replaced by a suffix of your choice

Close

Import

You can keep the default suffix (_imported_<date>) or replace it by a suffix of your choice.

2.3 Using the Service Logic Editor

2.3.1 Service Logic Nodes Description

An SRE service logic is made of interconnected nodes which create a flow of different branches that each call will traverse. This section describes nodes characteristics. The specific function of each node is further described in the separate document *Service Logic Nodes Description*.


2.3.1.1 Node categories and function

Nodes are grouped along the following categories and have the following functions:

- **Processing** nodes allow processing of the input data with a wide variety of operations.
- **Service sub-logic (macro)** nodes allow embedding an existing service logic as a sub-logic of the parent one.

- **Output** nodes allow selecting an appropriate SIP/ENUM/HTTP answer as output
- **Exit** nodes are the paths used to exit the service logic after processing of the input data. The result is returned to the call originator.


The picture below shows a simple example of two exit nodes in a Least Cost Routing service logic: Match / No Match.



2.3.1.2 Nodes graphical layout


The graphical representation of the nodes uses the following elements, which are common to the processing and sub-logic types.

- The **Processing** and **Service sub-logic** nodes have a label and a body, with one left connector (on the label's left edge) and one or more right connectors (on the body's right edge).



The label shows the user-given name. The second line in the label shows the built-in description of the node (which shows in the **New Node** page).

If a user description is provided, it will appear when mousing-over the label (third line, italics).








- The **Start** node only has the Start label and a right connector. It must be the leftmost node in the service logic line.
- The **Output** and **Exit** nodes have a label with the user-given name and the built-in description, and a left connector. They cannot be connected to a next node, only to one (or more) previous ones.


If a user description is provided, it will appear when mousing-over the label in the Build grid.

Clicking the name or description in the label of any existing node opens the **Edit node** screen, allowing to modify the user-given Name, Description and the elements defined.

2.3.1.3 Nodes color code

The graphical representation of the nodes on the grid uses the following colour code:


Node	Color	Example
Start	Green	
Processing	Blue label / Grey body	
Service sub-logic (macro)	Orange label / Grey body	
Output	Purple	
Exit	Dark Orange	

Node	Color	Example
Deprecated nodes	Red label / Grey body	

2.3.1.4 Deprecated nodes

Deprecated nodes are legacy nodes for which a better alternative is available in the current SRE release. Deprecated nodes in existing service logics keep being executed, but they cannot be used in service logics being created from scratch. They still are shown in the drop-down lists of nodes, but cannot be placed on the build grid.

The figure below shows 8 nodes of type *Database*; the 4 last ones, marked [deprecated], cannot be used in new service logic anymore.





The table « Deprecated node | Better alternative node » in the document *Service Logic Nodes Description* lists all deprecated nodes and their new version or alternative.

2.3.2 Changed in Rel 3.3: Mouse operations in the Build and Simulate Call tabs

Selecting and moving nodes and moving the entire viewport is possible through the following mouse operations:

- Wheel to scroll down or up vertically (or use the vertical elevator)
- Hold Ctrl-shift-wheel to zoom in or out
- Left click to draw a square selecting all the nodes within the square. When selected, left-click the background to deselect all, Ctrl-left click to deselect one.





- Ctrl-left click nodes successively to select several non-contiguous nodes. Ctrl-left click one to unselect it.
- Hold Ctrl-left click anywhere and drag to move the whole viewport.

2.3.3 Build tab

The **Build** tab allows creating/editing the service logic by placing / adding nodes on a grid and connecting them.

2.3.3.1 Placing a node on the Build grid

To create a node and place it on the grid:

1. Decide what type and what particular node you need
2. Adjust the zoom on the grid using the mouse wheel
3. Click **New node**, then the node category, then the node type.

4. Click **Next** to continue with node creation

or

Click **Stop** to exit.

5. Fill in the **Name** and **Description** fields.

The name is mandatory. Leaving the Description empty prohibits the display of the node information in the grid when mouse-hovering the node label (see [Nodes graphical layout](#) above).

6. Add appropriate elements or fill in other fields.

For more details on each node, please refer to this node in the document *Service Logic Nodes Description*.

7. To stop the node creation, click **Close** (or the X cross top right)

or

To save the values entered and create the node, click **Save**.

8. When done, the new node is placed on the grid.

2.3.3.2 Connecting / disconnecting nodes

When placed on the grid after creation, nodes are not yet connected to any existing node.

As shown above, in the Nodes colour code table, nodes have one or more right connectors and (except for the Start node) only one left connector.

The logic of a service logic is linear, from left to right: connections are created from the right connector(s) of a lefthand node to the left connector of a righthand node.

To create a connection, click a connector at the right side of the lefthand node: it turns red and a dotted line appears. Then click the left connector of the righthand node: it turns red and the connection is created.

To remove a connection, quietly click the lefthand connector twice. Double-click works but zooms in at the same time.

2.3.3.3 Editing a node

To edit an existing node, click its label. This opens the **Edit Node** window, allowing to modify the elements defined at node creation. It also allows removing the node or duplicating it. This last operation spares time when similar nodes with complex design are needed.

2.3.3.4 Saving a Service Logic

There is no specific action for saving, and no **Save** button. The logic is automatically saved after every modification.

2.3.4 Simulate call tab

Once the nodes are created, placed and connected, the service logic can be tested. This is done using the *Simulate call* tab.

Click this tab to display its page, then fill in the **Calling** and **Called** fields and optionally the **Counter**, then click **Run**.

By default, the simulation runs in the service logic you are in. It is also possible to simulate starting from the parent service logic (up to the main one).

The service logic is executed, and each node executed shows a sequence execution number, black if ok, red if not. Dotted animated lines show the path followed based on the input received and the connections (unconnected nodes cannot be executed).

Persist Call Descriptor: when checked, in case of multiple iterations (for example call crankback), the call descriptor of iteration n-1 is kept at the start of iteration n, and only the last operation is performed. This avoids repeating the processing (DB queries, etc.) already performed during the previous iteration.

Two elements bring more information about how the simulation has run:

- the Call Descriptors (one next to each executed node)
- The Simulation Timeline (below the grid).

2.3.4.1 The Call Descriptors

The picture below shows the Simulate Call grid after a simulation has run. The black (or red) steps are Call Descriptors.

Service Logic Editor / rben doc 3

Service Logic Editor


Build Simulate call Simulate SIP Validate Release Export Properties

Calling Counter

Called 2345 Persist call descriptor

Run Save simulation Simulation name

Steps



```
graph LR; Start([Start]) --> S1((1)); S1 --> D1[is emergency?]; D1 -- match --> S2((2)); D1 -- no match --> S3((3)); S2 --> E1[is emergency]; S3 --> E2[is not emergency]; E1 --> S3; E2 --> S3;
```

Dotted line: path followed

They are displayed when mousing over the numbered square and show the values before and after the considered step.

Service Logic Editor / rben doc 3

Service Logic Editor


Build Simulate call Simulate SIP Validate Release Export Properties

Calling


Called

Counter

Run Save simulation Simulation name



Clicking a step number in the viewport (instead of mousing over) opens a modal window for the clicked step, showing the data from the Call Descriptor.



2.3.4.1.1 New in Rel 3.3: Queries are logged in Call Descriptors of External Query nodes

For more details see *SRE Nodes Description* document.

2.3.4.1.2 New in Rel 3.3: SIP manipulations are logged in Call Descriptors of SIP nodes

When a SIP node performs an action, it's logged in the node's Call Descriptor:

Mouse over the step # shows the tip


Variable	Before	After
callId		
called		
calling		
counter	0	0
originalCalled		
originalCalling		

Jan 31 10:01:03.392: replaced in body regexp audio with video


Logged action

Some SIP manipulations append behind-the-scene actions which will be executed later on: if present, they are also displayed in the log summary of the output SIP node.

Mouse over the step number to see the tip of the Call Descriptor.



Click the step number to display the Call Descriptor window.



2.3.4.2 The Simulation Timeline

Click *Simulation Timeline* below the grid, bottom left, to display the table showing the sequence of steps, the duration for each step, the cumulative duration and the values of the processed variables.

Service Logic Editor / rben doc 3

Service Logic Editor

Build Simulate call Simulate SIP Validate Release Export Properties

Calling: Counter:

Called: Persist call descriptor

Simulation timeline

Step	1	2	3
Node	Start	is emergency?	is not emergency
Step duration	0.00 ms	0.36 ms	0.28 ms
Cumulative duration	0.00 ms	0.36 ms	0.64 ms
callId			
called	2345	2345	2345
calling			
counter			
originalCalled	2345	2345	2345
originalCalling			

In the timeline below, the value of the variable `called` has been modified at step 3 and is highlighted in pink, while the variable `new_variable` has received at step 4 a value for the first time and is highlighted in green.

Simulation timeline

Step	1	2	3	4	5
Node	Start	test DA	add 999	concatenate sample	reject with 404
Step duration	0.00 ms	0.79 ms	0.55 ms	0.76 ms	0.48 ms
Cumulative duration	0.00 ms	0.79 ms	1.33 ms	2.09 ms	2.58 ms
callId					
called	6789	6789	9996789	9996789	9996789
calling	2345	2345	2345	2345	2345
counter					
new_variable				FirstLast_9996789	FirstLast_9996789
originalCalled	6789	6789	6789	6789	6789
originalCalling	2345	2345	2345	2345	2345

2.3.4.2.1 New in Rel 3.3: Focus on a step in the Timeline


When the Timeline is shown on the screen (below the viewport), mouse over a step number in the

viewport not only shows the Call Descriptor tip, but also moves the focus of the Timeline, sliding the display from this step (when possible: mouse over the last step will show it last on the line).

The focus remains on the last step invoked by the mouse over until another step is invoked.

Compare the two screens below:


Mouse over step 2: tip and timeline starting with 2, not showing steps 11 to 13.



The screenshot displays a workflow diagram with 13 steps. A tooltip is open for step 2, showing variable values before and after the action. Below the diagram is a 'Simulation timeline' table.

Step	2	3	4	5	6	7	8	9	10	
Service logic	demo doc - log actions									
Node	rmv codecs	add H	rmv H	repl H	repl body	timer	new From	new To	append	
Step duration	0.26 ms	0.14 ms	0.07 ms	0.08 ms	0.07 ms	0.08 ms	0.08 ms	0.07 ms	0.06 ms	
Cumulative duration	0.26 ms	0.40 ms	0.47 ms	0.55 ms	0.62 ms	0.70 ms	0.78 ms	0.85 ms	0.90 ms	
callid										
called										
calling										
counter	0	0	0	0	0	0	0	0	0	
originalCalled										
originalCalling										

Mouse over step 13: tip and timeline showing step 13 (last step) on the right, not showing steps 1 to 4.




The screenshot displays a service logic flowchart with steps 7 through 13. Step 7 is 'timer Invite Timer', step 8 is 'new From Set From URI', step 9 is 'new To Set To URI', step 10 is 'append Append CDR fields', step 11 is 'set Set CDR fields', step 12 is 'RO Set RO fields', and step 13 is 'relay'. A variable table is shown on the right, and a simulation timeline table is at the bottom.

Variable	Before	After
callId		
called		
calling		
counter	0	0
originalCalled		
originalCalling		

Step	5	6	7	8	9	10	11	12	13
Service logic			demo doc - log actions						
Node	repl H	repl body	timer	new From	new To	append	set	RO	relay
Step duration	0.08 ms	0.07 ms	0.08 ms	0.08 ms	0.07 ms	0.06 ms	0.05 ms	0.07 ms	0.41 ms
mutative duration	0.55 ms	0.62 ms	0.70 ms	0.78 ms	0.85 ms	0.90 ms	0.95 ms	1.03 ms	1.43 ms
callId									
called									
calling									
counter	0	0	0	0	0	0	0	0	0
originalCalled									
originalCalling									

2.3.4.2.2 New in Rel 3.3 - Frozen headers in Timeline table

When the number of rows in the table exceeds the table height, the top lines are kept on screen while the vertical scroll displays the last rows.



Simulation timeline

Step	1	2									
Service logic	demo doc - frozen simulation headers										
Node	Start	crl									
Step duration	0.00 ms	0.23 ms									
Cumulative duration	0.00 ms	0.23 ms									
callId											
called											
calling											
counter	0	0									
originalCalled											
originalCalling											
rl		<table border="1"> <thead> <tr> <th>column1</th> </tr> </thead> <tbody> <tr><td>a</td></tr> <tr><td>b</td></tr> <tr><td>c</td></tr> <tr><td>d</td></tr> <tr><td>e</td></tr> <tr><td>f</td></tr> <tr><td>g</td></tr> <tr><td>h</td></tr> </tbody> </table>	column1	a	b	c	d	e	f	g	h
column1											
a											
b											
c											
d											
e											
f											
g											
h											

0:1

[img/sim

2.3.4.3 Saving a simulation

You can save a simulation if you want:

- to replay the service logic with the same values entered, and compare the new simulation with the saved one
- to load the simulation, enter different values and compare the new results with the saved ones
- to group simulations and run them as a whole in « batch » mode.

To save a simulation, enter a name for it (must be unique) and click **Save** button. The operation is confirmed.

Note

Saving a simulation saves the input values (provided in Calling / Called fields), and the output values resulting from the process applied by the service logic.

No link is kept between a saved simulation and the service logic originally selected to run it. The logic behind the un-binding between simulations and service logics is that a given simulation can be used with several different service logics, for example, the releases or development versions of the same service logic.

Loading (from *Validate* tab) **and running** again (in *Simulate call* tab) a saved simulation *with a service logic different from the one used to run and save it first* will most probably end up with different results.

Similarly, **replaying** a simulation (from *Validate* tab) will use the currently selected service logic: the results are compared with the ones saved and differences, if any, are highlighted (see [Validate tab](#) below).

It may be advisable to save simulations under names that have some reference to the original service logic, and to make sure that the same original service logic that was used in the first place is the one selected when running again or replaying a saved simulation.

To load or replay a saved simulation, to group simulations or to run a simulations group, go to *Validate* tab (see [Validate tab](#) below.)


2.3.5 Simulate SIP tab

The *Simulate SIP* tab is similar to the *Simulate Call* tab above, but instead of simply providing Calling / Called values as input for a simulation, it allows defining the following elements:

- Source (IP) address and port


- Destination (IP) address and port
- A full SIP message to be processed by the service logic
- Operational conditions of the SIP Agents
- Counter: set it to 0 to simulate a first call attempt; set it to 1, 2,... to simulate crank-back calls
- Persistent call descriptor: when doing crank-back simulations (counter=N), set this flag on to be able to use a call descriptor calculated by previous runs (counter=0,...,N-1).

By default, the simulation runs in the service logic you are in. It is also possible to simulate starting from the parent service logic (up to the main one).




As SIP operations are being processed, the status of SIP Agents can be set as expected by the operations to be performed during service logic simulation:

- The *Load status from* drop-down list shows the Call Processing nodes present and allows selecting one to load the SIP Agents status from:



- The *Modify status* drop-down list allows manually setting the status of each of the SIP Agents monitored by the Call Processing nodes.




The operations (Run, Save Simulation) and information returned (Call Descriptors, Simulation Timeline) behave exactly as described above in [Simulate call tab](#).

2.3.6 Simulate ENUM tab

The *Simulate ENUM* tab is useful to test ENUM-related service logic. It allows defining the following elements:

- Number/zone: phone number and enum zone (e.g. e164.arpa)

By default, the simulation runs in the service logic you are in. It is also possible to run the simulation from the parent service logic (up to the main one).




You can save the simulation inputs and outcomes.

2.3.7 Simulate HTTP tab

The *Simulate HTTP* tab is useful to test HTTP-related service logic. It allows defining the following elements:

- Method: GET, POST, PUT, PATCH, DELETE
- Path
- Body: Some methods require a body to be defined with the content of the request

By default, the simulation runs in the service logic you are in. It is also possible to run the simulation from the parent service logic (up to the main one).




2.3.8 Simulate CDR tab

The *Simulate CDR* tab allows applying the operations of a service logic to a single CDR used as input, and optionally to output the results to an Output CDR node (see separate *SRE Nodes Description* document).

The only possible input for the **CSV row** field is a single line that is the CDR in comma-separated format.

Clicking **Run** executes the service logic, showing the steps in numbered black squares in the grid.



At the bottom, the **Simulation Timeline** button displays the successive values of each variable in each step. Cells with a green background show values changed from the previous step. A horizontal scroll bar at the bottom allows navigating the Simulation timeline columns, which correspond to the steps in the grid.

Step	3	4	5
Service logic	Rating	Final cost	Output node
Node	Find rate	Final cost	Output node
Step duration	233.12 ms	0.79 ms	0.78 ms
Cumulative duration	233.69 ms	234.48 ms	235.26 ms
answer_cost	3.45	3.45	3.45
callid	163550-4422	163550-4422	163550-4422
connectHost	sre3-cp-lab-fleg	sre3-cp-lab-fleg	sre3-cp-lab-fleg
connectTime	2021-02-24 15:35:57.796163	2021-02-24 15:35:57.796163	2021-02-24 15:35:57.796163
contact			
counter	0	0	0
custom0	trunk-mobile1	trunk-mobile1	trunk-mobile1
custom1	OLO2-mobile	OLO2-mobile	OLO2-mobile
customer	Dummy_Bank	Dummy_Bank	Dummy_Bank
destinationAddress	10.0.161.91	10.0.161.91	10.0.161.91
destinationPort	5060	5060	5060
destination_name	Belgium Mobile	Belgium Mobile	Belgium Mobile
disconnectHost	sre3-cp-lab-fleg	sre3-cp-lab-fleg	sre3-cp-lab-fleg
disconnectTime	2021-02-24 15:41:03.954335	2021-02-24 15:41:03.954335	2021-02-24 15:41:03.954335
duration	45	45	45
final_cost		4.5375	4.5375
fromURI	sip:anonymous@anonymous.local	sip:anonymous@anonymous.local	sip:anonymous@anonymous.local
fromUsername	anonymous	anonymous	anonymous
lastRequestURI	sip:trunk-mobile1;trunk-context=OLO2-mobile@hdmobile.pxm.be	sip:trunk-mobile1;trunk-context=OLO2-mobile@hdmobile.pxm.be	sip:trunk-mobile1;trunk-context=OLO2-mobile@hdmobile.pxm.be
number_range	+3247	+3247	+3247
perminute_cost	1.45	1.45	1.45
requestURI	sip:0472801896@blabla.com	sip:0472801896@blabla.com	sip:0472801896@blabla.com

Example of a source CDR

2021-02-24T15:35:51.591781,sre3-cp-lab-fleg,2021-02-24T15:35:57.796163,sre3-cp-lab-fleg,0,163550-4422,0,sip:anonymous@anonymous.local,anonymous,sip:0472801896@blabla.com,+32472801896,sip:0472801896@blabla.com,0472801896,sip:C49000472801896;tgrp=trunk-mobile1;trunk-

↪ context=mobile@customer.be, 10.0.161.170,5060,10.0.161.91,5060,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,
 ↪ trunk-mobile1,0L02-mobile

2.3.9 Validate tab


The *Validate* tab is the location in the SRE GUI where you can manage saved simulations, to load and run them, replay them, to associate them into groups and to run groups of simulations (so to speak, in « batch » mode).

Note

Remember that whatever actions you take with simulations, they will be run or replayed through the currently selected service logic (the last one chosen in *Service Logic List* page).

2.3.9.1 Viewing saved simulations

The *Validate* tab displays first the list of simulations saved on the system. The usual controls allow refining the list: number of entries per page (*Show nn entries*, top left) , *Search* field (top right), navigation buttons (bottom right).



The information is presented in the following columns:

- **Name:** the name used to save the simulation (not: the name of the service logic)
- **Group:** the name of the simulations group the simulation belongs to (if any). You will use this list of groups to associate a simulation with a group.
- **Type:** call (a simple call simulation run and saved from the *Simulate call* tab), or sip (a SIP simulation run and saved from the *Simulate SIP* tab).

- **Saved:** the date when the simulation has been saved.
- **Input:** either the Calling / Called values used as input for a Call Simulation, or the SIP message used as input for a SIP Simulation.
- **Call Descriptor:** the full list of variables and values processed by the service logic, shown in two tables: Input (values provided at Start) and Output (after service logic execution, the resulting values and result returned to the call originator)

Service Logic Editor

Build Simulate call Simulate SIP Validate Release Export Properties

Group Filter: rben doc 1 simgroup

Show 5 entries

Search: |groupid:1:

Name	Group	Type	Saved	Input	Call Descriptor	Load	Replay	Remove
rben doc 1/A	rben doc 1 simgroup	call	2019-11-06 15:47:04	Calling: 123 Called: 458		Load	Replay	Delete
rben doc 1/B	rben doc 1 simgroup	call	2019-11-06 15:49:16	Calling: 123 Called: 456		Load	Replay	Delete


Variable	Value
counter	
called	456
calling	123

Variable	Value
originalCalled	456
callId	
counter	
originalCalling	123
calling	123
called	456
Service execution result	403 Forbidden

Showing 1 to 2 of 2 entries (filtered from 23 total entries)

Previous 1 Next


- **Load** button: loads the simulation in the corresponding *Simulate Call* tab or *Simulate SIP* tab, to re-run it there (no results comparison).
- **Replay** button: replays the simulation and displays the comparison in a **Simulation Replay Result** modal window, showing the INPUT and OUTPUT list of variables and the values provided or processed by the saved simulation and the replayed one. Top banner (highlighted in green) indicates if the saved and replayed results are equal.



- **Delete** button: deletes the saved simulation from the system (with Yes/No confirmation).


2.3.9.2 Grouping simulations and running them

At the top of the list of simulations, two elements allow managing groups of simulations.




The **Group Filter** drop-down list shows the groups already defined and allows filtering the list below to show only the simulations belonging to this group. You associate a simulation with a group by selecting this group from the list in the **Group** column (circled in orange above).

The **Manage simulation groups** button opens the modal window below:



From this window, you can:

- replay a group of simulations (click **Replay** button: the results show in a modal window).




- delete a simulations group (click **Delete** button - only the «label» is deleted, the simulations are not)
- create a new simulations group (provide a name for the group and click **Create** button)
- rename a simulation group (click its name in the **Name** column).

2.3.9.3 New in Rel 3.3 – Exporting / importing simulations


Simulations can be exported from the active service logic to a file stored on a local system, or imported from such a file into the active service logic. This allows re-using simulations on a different deployment.

These operations are executed through the action buttons **Export [...]** and **Import** at the bottom left of the *Validate / Simulations list*, as shown below.



The screenshot shows the Service Logic Editor interface. At the top, there are tabs for 'Simulate call', 'Simulate SIP', 'Simulate ENUM', 'Simulate HTTP', 'Simulate CDR', 'Validate', and 'Traces'. Below the tabs is a 'Group Filter' dropdown set to 'Any' and a 'Manage simulation groups' button. A 'Show 5 entries' dropdown is visible. The main area contains a table of simulation entries with columns for Name, Group, Type, Saved, Input, Call Descriptor, Load, Replay, and Remove. The table lists several simulation entries, including 'HTTP SBC Stir/Shaken request', 'Test FCAR demo', and several 'call 1' entries. At the bottom left, the text 'Showing 1 to 5 of 6 entries' is displayed above two buttons: 'Export filtered' and 'Import'. A green arrow points to the 'Import' button.

The list of simulations can be filtered using the *Search* field on the top right. The information just above the **Export / Import** buttons (bottom left) shows if the displayed list is filtered or not.




This screenshot shows the same Service Logic Editor interface as the previous one, but with a search filter applied. The 'Search:' field at the top right now contains the text 'call'. The table below shows only four simulation entries that match the search criteria. At the bottom left, the text 'Showing 1 to 4 of 4 entries (filtered from 6 total entries)' is displayed above the 'Export filtered' and 'Import' buttons. A green arrow points to the 'Search:' field, and another green arrow points to the 'Showing 1 to 4 of 4 entries (filtered from 6 total entries)' text.


The **Export** button allows exporting:

a) the simulations in the filtered list. The button is labelled **Export filtered**. This will export the simulations in the filtered list to a file named `simulations_filtered_<date-time stamp>.simulations`. You can save this file anywhere on your local system (and possibly move it to another deployment).

b) all the simulations in the (unfiltered) list. Use the drop-down arrow (see image below) and select **Export all**. This will export all the simulations, even if the list is currently filtered, to a file named `simulations_<date-time stamp>.simulations`. You can save this file anywhere on your local system (and possibly move it to another deployment).




To import simulations (usually coming from another deployment), click the **Import** button. This opens the *Import Simulations* sub-window, where you have to specify what you want to import.



- **File:** select on your local system a simulations file previously exported.
- **Groups**
 - **Import:** check the box to confirm that you want to import the groups the simulations belong to. Leave blank to avoid group import.

Note

If groups are not imported [– No Group –] for a simulation, they still can be associated manually in the top part of the *Validate* tab:



- **Skip existing:** check the box to avoid overwriting a group name already existing.
- Suffix:** if left empty and there is a naming conflict between existing groups and imported groups, the imported groups are suffixed (1), (2), etc. To use a different suffix, simply type it.

- **Simulations**

- **Import:** check the box to confirm that you want to import the simulations (this is actually what you are expected to want if you are here).
 - **Skip existing:** check the box to avoid overwriting simulations already existing.
- Suffix:** if left empty and there is a naming conflict between existing simulations and imported simulations, the imported simulations are suffixed (1), (2), etc. To use a different suffix, simply type it.

When all your selections are set, you can use the **Close** button to cancel the operation or the **Import** button to execute it.

2.3.10 Traces tab

The content of the *Traces* tab is defined in the *System > Tracing* setting.

Note

- If no criteria are defined in *System / Tracing* tab, the *Traces* tab will remain empty.
- At least one real or simulated SIP call or one HTTP/ENUM trigger must match the criteria in *System / Tracing* for any trace to appear in the *Traces* tab.

When a SIP/ENUM/HTTP transaction matches the criteria defined in the *Tracing* tab, a new trace appears in the *Traces* tab of the corresponding active Service logic for SIP/ENUM/HTTP.

- The number of traces visible here is limited by the setting in *System > Settings > GUI > Max number of traces stored in-memory*.
- Once a Trace is available, the user can click on *Call Descriptor* or *Show*:
 - *Call Descriptor*: it shows the call descriptor for the traced call, with particular attention to the outcome *Service Execution result* (it could be e.g. relay to... or redirect to ...)
 - *Show*: it replays the call into the Simulation tab of the Service Logic, provides a graphical view of the traversed nodes and the full Simulation tab at the bottom of the page.
- Traces are automatically rotated by the system when they reach the max number of traces stored in memory.

2.3.11 Release tab

Releasing a service logic consists in creating a frozen, not editable version of it, normally for use in production.

To release a service logic, provide a name and description for the released version and click **Create Release** button. The released service logic is created and can be accessed in the *Releases* tab of the **Service Logic List** page (see above [Development vs Releases](#)).

Released service logic cannot be modified (edited) but it can be instantiated, i.e. a new editable service logic will be created from the released one and will become available for edition in the *Development* tab of the **Service Logic List** page.

To instantiate a released service logic, click the **Instantiate** button on the desired line in the *Releases* tab of the **Service Logic List** page, provide a name for it and go find it in the *Development* tab of the same page.

2.3.12 Export tab


The *Export* tab presents an **Export** button which saves the service logic being edited into a local <name>-of-service-logic>.slid file for import into another SRE system (see *Import* button in [Service Logic List](#)).

2.3.13 Properties tab

The *Properties* tab displays a form allowing to modify the current Name and Description of the service logic being edited.

2.4 Selecting service logics for operations

From the main menu bar, select **Service Logic** to open the menu, then **Service Selection** to open the **Service Selection** page.




2.4.1 Changed in Rel 3.3: Service Selection

When opened, the page displays the *Service Selection* form, with the first link in the left panel active (*Service Logic Selection*, blue background). The form lists the interfaces configured on the system and allows selecting the version of the service logic that will be active for each interface.

Custom endpoints created for SIP or HTTP interfaces in the third tab on the left (see below [Changed in Rel 3.3: Custom Endpoints for SIP and HTTP](#)) appear in this list, as well as default endpoints.

The drop-down lists in the **Active Version** column display all the service logics available on the system and allow selecting one of them. The indication between brackets after the service logic name shows its version type: (development) or (release name and version).



The screenshot shows the 'Service Selection' interface. On the left, there is a sidebar with 'Service Logic Selection' selected. The main area is titled 'SERVICE LOGIC SELECTION' and contains a table with two columns: 'Interface' and 'Active Version'. The 'SIP' interface is selected, and its details are shown below. The 'Active Version' column contains dropdown menus for each interface. A blue box highlights the 'SIP: INVITE' entries, and a blue arrow points to the dropdown menu in the 'Active Version' column. A blue arrow also points to the 'Custom Endpoints' link in the sidebar.

Select the Active Version appropriate for each interface, then click **Save** button when done.

2.4.1.1 Probing SIP peers: Custom Agents Probing

SRE 3.2 brings in an alternative way of probing SIP peers in SRE, still using SIP OPTIONS as in the original feature, but expanding the possibilities to customize the SIP message headers and parameters.

Within the section *Service Logic > Service Selection > Service Logic Selection*, the user can now select a specific SL for Custom Agents probing.

This logic has to be designed in a similar way as any other Service Logic.

The principle is to create an array of records (record list) containing:

- the name of the sip peer
- the IP address
- the port (default 5060)
- the transport (default UDP)
- the Request-Uri (default <remoteIP>:<remotePort>)
- the From URI (default sip:ping@<localIP>)
- the To URI (default sip:ping@<remoteIP>)

2.4.1.2 CDR Post-processing


CDR Post-processing allows the user to build brand-new tailored CDRs, starting from SRE default CDRs. The default CDR fields are passed to the selected Service Logic for CDR Post-Processing in the form of variables of a call descriptor. The purpose of such Service Logic is to create an Output CDR row, which contains the selected fields (Columns).

The post-processed CDRs are then stored in the directory configured in *System > Settings > Accounting > SIP accounting post-processing output directory* (default dir: `/data/sre/accounting/postprocessing` → /) for further use.

2.4.2 Service Logic Node Override

The second link in the left part, *Service Logic Node Override*, displays the form below. It lists again the interfaces configured on the system, together with the Call Processing nodes, for each interface a selection list allowing to pick for each node a service logic **different from the default one** (the one selected in the *Service Logic Selection* form described above).

If applicable, select an Active Version different from the default one for a particular interface on one of the Call Processing nodes. Click **Save** button when done.



Service Selection

Service Logic Selection

Service Logic Node Override

Custom Endpoints

SERVICE LOGIC NODE OVERRIDE

Interface sre3.1-testbed

SIP	<- Default Service Logic ->
SIP Reply	<- Default Service Logic ->
Enum	<- Default Service Logic ->
HTTP	<- Default Service Logic ->
Custom agents probing	<- Default Service Logic ->
CDR post-processing	<- Default Service Logic ->

Save

Released versions are frozen and can not be edited. Development versions can be edited in the Service Logic Editor and changes are applied immediately to new requests. Changes might take up to 60 seconds to be refreshed on all elements.

These settings complete the setup of the service logic selection for the SRE to operate in production conditions.

2.4.3 Changed in Rel 3.3: Custom Endpoints for SIP and HTTP

The third link in the left part, *Custom Endpoints*, allows for defining custom endpoints for SIP (specific SIP messages based on the SIP Method (INVITE, REGISTER, UPDATE, NOTIFY, ...)) or HTTP (specific

URLs), to which a specific Service Logic can be set (see above the *Service Logic Selection* tab). This is a powerful way to trigger different behaviours for different methods (for example, HTTP method GET as opposed to PUT as opposed to POST) or even for the same method and different URLs.

The **Custom Endpoints** list allows the creation of new custom endpoints, lists the endpoints already defined and allows removing them.

For SIP endpoints:

- Match type: dropdown list to select the type: source/destination address and port, From or R-URI range, Regexp
- Match value: the value to consider for the selected type
- Priority: in the case of multi-match, the highest priority wins.

SIP
HTTP

NEW CUSTOM ENDPOINT

Method

Match type

Match value

Priority

[Create](#)

CUSTOM ENDPOINTS

Show entries Search:

Method	Match type	Match value	Priority	Delete
INVITE	Source address and port	10.0.161.186	0	Delete
INVITE	From username range	39-23	3	Delete
INVITE	Source address and port	10.1.1.1:5060	5	Delete

Showing 1 to 3 of 3 entries
[First](#)
[Previous](#)
1
[Next](#)
[Last](#)

For HTTP endpoints:

SIP
HTTP

NEW CUSTOM ENDPOINT

Method

URL

Create

CUSTOM ENDPOINTS

Show entries Search:

Method	URL	Delete
GET	/	Delete
GET	/stirshaken/as	Delete
POST	/stirshaken/as	Delete
PUT	/stirshaken/as	Delete

Showing 1 to 4 of 4 entries

1

Based on the matching of these criteria, a specific SL execution will be launched, according to Service Selection (with a dropdown list for each endpoint created here, see [Changed in Rel 3.3: Service Selection](#) above).